

TEAMSPEAK 3

SERVERQUERY MANUAL (2009-12-04)



COPYRIGHT ©2009 TEAMSPEAK SYSTEMS GMBH

CONTENT

Content	1
Introduction	4
How to Establish a ServerQuery Connection	4
Command Syntax	4
Summary of Command Syntax	4
Examples of Command Syntax	4
Escaping	5
Command Reference	6
help	6
quit	6
login	6
logout	6
version	7
hostinfo	7
instanceinfo	7
instanceedit	7
bindinglist	8
use	8
serverlist	8
serveridgetbyport	8
serverdelete	9
servercreate	9
serverstart	9
serverstop	9
serverprocessstop	10
serverinfo	10
serverrequestconnectioninfo	10
serveredit	10
servergrouplist	11
servergroupadd	11
servergroupdel	11
servergrouprename	12
servergrouppermlist	12
servergroupaddperm	12
servergroupdelperm	12
servergroupaddclient	13
servergroupdelclient	13
servergroupclientlist	13
servergroupsbyclientid	13
serversnapshotcreate	14
serversnapshotdeploy	14
servernotifyregister	14
servernotifyunregister	14

gm	15
sendtextmessage	15
logview	15
logadd	16
channellist	16
channelinfo	16
channelfind	16
channelmove	17
channelcreate	17
channeledit	17
channeldelete	18
channelpermlist	18
channeladdperm	19
channeldelperm	19
channelgrouplist	19
channelgroupadd	19
channelgroupdel	20
channelgrouprename	20
channelgroupaddperm	20
channeldelperm	20
channelgrouppermlist	21
channelgroupclientlist	21
setclientchannelgroup	21
clientlist	21
clientinfo	22
clientfind	22
clientedit	22
clientdblist	22
clientdbfind	23
clientdbedit	23
clientdbdelete	23
clientgetids	23
clientgetdbidfromuid	24
clientgetnamefromuid	24
clientgetnamefromdbid	24
clientsetserverquerylogin	24
clientupdate	24
clientmove	25
clientkick	25
clientpoke	25
clientpermlist	25
clientaddperm	26
clientdelperm	26
channelclientpermlist	26
channelclientaddperm	26
channelclientdelperm	27
permissionlist	27
permoverview	27
permfind	27
tokenlist	28
tokenadd	28
tokendelete	28
tokenuse	28
messagelist	29
messageadd	29
messageget	29
messageupdateflag	29

messagedel	29
complainlist	30
complainadd	30
complaindel	30
complaindelall	30
banclient	31
banlist	31
banadd	31
bandel	31
bandelall	32
ftinitupload	32
ftinitdownload	32
ftlist	33
ftgetfilelist	33
ftgetfileinfo	33
ftstop	33
ftdeletefile	34
ftcreatedir	34
ftrenamefile	34
whoami	34
Server Instance Properties	35
Virtual Server Properties	36
Channel Properties	39
Client Properties	40
Definitions	42

INTRODUCTION

ServerQuery is a command-line interface built into the *TeamSpeak 3 Server* which allows powerful scripting and automation tools to be built based on the exact same instruction set and functionality provided by the *TeamSpeak 3 Client*. For example, you can use scripts to automate the management of virtual servers or nightly backups. In short, you can perform operations more efficiently by using *ServerQuery* scripts than you can by using a user interface.

This manual describes the general *ServerQuery* usage and syntax and provides examples for all commands available.

HOW TO ESTABLISH A SERVERQUERY CONNECTION

Connecting to a *ServerQuery* interface can be done by using a character-mode terminal client such as *Telnet* or *PuTTY*. Basically, a *ServerQuery* client is acting like a real client, except it's unable to send or receive voice data.

Per default, the *TeamSpeak 3 Server* is waiting for incoming *ServerQuery* connections on port *10011* (TCP). On success, the server should welcome you with a TS3 prompt.

COMMAND SYNTAX

This section describes the syntax of all *ServerQuery* commands.

SUMMARY OF COMMAND SYNTAX

ServerQuery commands follow the general syntax of:

```
command [parameter...] [option...]
```

The command is a single word which may contain lowercase letters, digits and underscore symbols (a-z 0-9 _) followed by a whitespace. A parameter block is made up of one or more key-value pairs separated by a whitespace. In addition, various commands support options which are specified with a leading minus. For example:

```
command key1=value1 key2=value2 -option1 -option2
```

Some commands accept grouped or nested parameters. Therefore allowing you to apply an action on more than one object. Those parameters are separated by a pipe symbol (|). For example:

```
command key1=value1|key1=value2|key1=value3
```

The pipe symbol (|) is also used to separate list items (e.g. multiple clients in a virtual servers `clientlist`).

EXAMPLES OF COMMAND SYNTAX

The following provides some common *ServerQuery* syntax examples:

```
serverlist
clientlist -uid -away -groups
clientdbfind pattern=ScP
clientdbfind pattern=FPMPSC6MXqXq751dX7BKV0JniSo= -uid
clientkick clid=1|clid=2|clid=3 reasonid=5 reasonmsg=Go\saway!
channelmove cid=16 cpid=1 order=0
sendtextmessage targetmode=2 target=12 msg=Hello\sWorld!
```

ESCAPING

You cannot use whitespaces or any special characters in parameters. Instead, the *TeamSpeak 3 Server* supports the use of escape patterns which can be used to insert newlines, tabs or other special characters into a parameter string. The same escape patterns are used to clean up the servers output and prevent parsing issues.

Here's an example on how to escape a parameter string correctly.

RIGHT:

```
serveredit virtualserver_name=TeamSpeak\s]\p[\sServer
```

WRONG:

```
serveredit virtualserver_name=TeamSpeak ]|[ Server
```

The following characters need to be escaped if they are to be used:

NAME	CHAR	ASCII	REPLACE CHAR	REPLACE ASCII
Backslash	\	92	\\	92 92
Slash	/	47	\/	92 47
Whitespace	" "	32	\s	92 115
Pipe		124	\p	92 112
Bell	\a	7	\a	92 97
Backspace	\b	8	\b	92 98
Formfeed	\f	12	\f	92 102
Newline	\n	10	\n	92 110
Carriage Return	\r	3	\r	92 114
Horizontal Tab	\t	9	\t	92 116
Vertical Tab	\v	11	\v	92 118

COMMAND REFERENCE

This is a list of the commands available when using the *TeamSpeak 3 ServerQuery* interface.

HELP

Provides information about *ServerQuery* commands. Used without parameters, `help` lists and briefly describes every command.

Permissions:

`b_serverinstance_help_view`

Syntax:

`help [{command}]`

Example:

```
help serverinfo
Usage: serverinfo
```

Displays detailed configuration information about a virtual server including ID, number of clients online, configuration, etc.

```
error id=0 msg=ok
```

QUIT

Closes the *ServerQuery* connection to the *TeamSpeak 3 Server* instance.

Syntax:

`quit`

Example:

```
quit
```

LOGIN

Authenticates with the *TeamSpeak 3 Server* instance using given *ServerQuery* login credentials.

Related Permissions:

`b_serverquery_login`

Syntax:

```
login client_login_name={username} client_login_password={password}
login {username} {password}
```

Example:

```
login client_login_name=xyz client_login_password=xyz
error id=0 msg=ok
```

LOGOUT

Deselects the active virtual server and logs out from the server instance.

Permissions:

`b_serverquery_login`

Syntax:

`logout`

Example:

```
logout
error id=0 msg=ok
```

VERSION

Displays the servers version information including platform and build number.

Permissions:

b_serverinstance_version_view

Syntax:

version

Example:

```
version
  version=3.0.0-alpha03 build=8779 platform=Linux
  error id=0 msg=ok
```

HOSTINFO

Displays detailed connection information about the server instance including uptime, number of virtual servers online, traffic information, etc.

For detailed information, see [Server Instance Properties](#).

Permissions:

b_serverinstance_info_view

Syntax:

hostinfo

Example:

```
hostinfo
  instance_uptime=1903203 host_timestamp_utc=1259337246 virtualservers_running_total=1
  connection_filetransfer_bandwidth_sent=0 ...
  error id=0 msg=ok
```

INSTANCEINFO

Displays the server instance configuration including database revision number, the file transfer port, default group IDs, etc.

For detailed information, see [Server Instance Properties](#).

Permissions:

b_serverinstance_info_view

Syntax:

instanceinfo

Example:

```
instanceinfo
  serverinstance_database_version=11 serverinstance_filetransfer_port=30033
  serverinstance_template_guest_serverquery_group=1 serverinstance_template_serveradmin_group=3 ...
  error id=0 msg=ok
```

INSTANCEEDIT

Changes the server instance configuration using given properties.

For detailed information, see [Server Instance Properties](#).

Permissions:

b_serverinstance_modify_settings

Syntax:

instanceedit [instance_properties...]

Example:

```
instanceedit serverinstance_filetransfer_port=1337
  error id=0 msg=ok
```

BINDINGLIST

Displays a list of IP addresses used by the server instance on multi-homed machines.

Permissions:

b_serverinstance_binding_list

Syntax:

bindinglist

Example:

```
bindinglist
  ip=0.0.0.0
  error id=0 msg=ok
```

USE

Selects the virtual server specified with `sid` to allow further interaction. The *ServerQuery* client will appear on the virtual server and acts like a real *TeamSpeak 3 Client*, except it's unable to send or receive voice data.

Permissions:

b_virtualserver_select

Syntax:

```
use sid={serverID}
use {serverID}
```

Example:

```
use sid=1
  error id=0 msg=ok
```

SERVERLIST

Displays a list of virtual servers including their ID, status, number of clients online, etc. If you're using the `-all` option, the server will list all virtual servers stored in the database. This can be useful when multiple server instances with different machine IDs are using the same database.

Permissions:

b_serverinstance_virtualserver_list

Syntax:

```
serverlist [-all]
```

Example:

```
serverlist
  virtualserver_id=1 virtualserver_port=9987 virtualserver_status=online virtualserver_clientsonline=6 ...
  error id=0 msg=ok
```

SERVERIDGETBYPORT

Displays the database ID of the virtual server running on the UDP port specified by `virtualserver_port`.

Permissions:

b_serverinstance_virtualserver_list

Syntax:

```
serveridgetbyport virtualserver_port={serverPort}
```

Example:

```
serveridgetbyport virtualserver_port=9987
  server_id=1
  error id=0 msg=ok
```


SERVERDELETE

Deletes the virtual server specified with `sid`. Please note that only virtual servers in stopped state can be deleted.

Permissions:

`b_virtualserver_delete`

Syntax:

```
serverdelete sid={serverID}
```

Example:

```
serverdelete sid=1
error id=0 msg=ok
```

SERVERCREATE

Creates a new virtual server using the given properties and displays its ID and initial administrator token. If `virtualserver_port` is not specified, the server will test for the first unused UDP port.

For detailed information, see [Virtual Server Properties](#).

Permissions:

`b_virtualserver_create`

Syntax:

```
servercreate virtualserver_name={serverName} [virtualserver_properties...]
```

Example:

```
servercreate virtualserver_name=TeamSpeak\s]\p[\sServer virtualserver_port=9988
virtualserver_maxclients=32
sid=2 token=eKnFZQ9EK7G7MhtuQB6+N2B1PNZZ60ZL3ycDp20W
error id=0 msg=ok
```

SERVERSTART

Starts the virtual server specified with `sid`. Depending on your permissions, you're able to start either your own virtual server only or all virtual servers in the server instance.

Permissions:

`b_virtualserver_start_any`

`b_virtualserver_start`

Syntax:

```
serverstart sid={serverID}
```

Example:

```
serverstart sid=1
error id=0 msg=ok
```

SERVERSTOP

Stops the virtual server specified with `sid`. Depending on your permissions, you're able to stop either your own virtual server only or all virtual servers in the server instance.

Permissions:

`b_virtualserver_stop_any`

`b_virtualserver_stop`

Syntax:

```
serverstop sid={serverID}
```

Example:

```
serverstop sid=1
error id=0 msg=ok
```

SERVERPROCESSSTOP

Stops the entire *TeamSpeak 3 Server* instance by shutting down the process.

Permissions:

b_serverinstance_stop

Syntax:

serverprocessstop

Example:

```
serverprocessstop
error id=0 msg=ok
```

SERVERINFO

Displays detailed configuration information about the selected virtual server including unique ID, number of clients online, configuration, etc.

For detailed information, see [Virtual Server Properties](#).

Permissions:

b_virtualserver_info_view

Syntax:

serverinfo

Example:

```
serverinfo
virtualserver_port=9987 virtualserver_unique_identifier=zrPkjznB1tMnRwj01xx7RxXjqeY=
virtualserver_name=TeamSpeak\s]I[\sServer ...
error id=0 msg=ok
```

SERVERREQUESTCONNECTIONINFO

Displays detailed connection information about the selected virtual server including uptime, traffic information, etc.

Permissions:

b_virtualserver_connectioninfo_view

Syntax:

serverrequestconnectioninfo

Example:

```
serverrequestconnectioninfo
connection_filetransfer_bandwidth_sent=0 connection_filetransfer_bandwidth_received=0
connection_packets_sent_total=241454 ...
error id=0 msg=ok
```

SERVEREDIT

Changes the selected virtual servers configuration using given properties.

For detailed information, see [Virtual Server Properties](#).

Permissions:

b_virtualserver_modify_name
b_virtualserver_modify_welcomemessage
b_virtualserver_modify_maxclients
b_virtualserver_modify_password
b_virtualserver_modify_default_servergroup
b_virtualserver_modify_default_channelgroup
b_virtualserver_modify_default_channeladmingroup
b_virtualserver_modify_ft_settings
b_virtualserver_modify_ft_quotas
b_virtualserver_modify_channel_forced_silence

b_virtualserver_modify_complain
b_virtualserver_modify_antiflood
b_virtualserver_modify_hostmessage
b_virtualserver_modify_hostbanner
b_virtualserver_modify_hostbutton

Syntax:

```
serveredit [virtualserver_properties..]
```

Example:

```
serveredit virtualserver_name=TeamSpeak\s]\p[\sServer virtualserver_maxclients=32  
error id=0 msg=ok
```

SERVERGROUPLIST

Displays a list of server groups available. Depending on your permissions, the output may also contain global ServerQuery groups and template groups.

Permissions:

b_serverinstance_modify_querygroup
b_serverinstance_modify_templates
b_virtualserver_servergroup_list

Syntax:

```
servergroup1ist
```

Example:

```
servergroup1ist  
sgid=9 name=Server\sAdmin type=1 iconid=300 savedb=1|sgid=10 name=Normal type=1 iconid=0 savedb=1|sgid=11 ...  
error id=0 msg=ok
```

SERVERGROUPADD

Creates a new server group using the name specified with name and displays its ID.

Permissions:

b_virtualserver_servergroup_create

Syntax:

```
servergroupadd name={groupName}
```

Example:

```
servergroupadd name=Server\sAdmin  
sgid=13  
error id=0 msg=ok
```

SERVERGROUPDEL

Deletes the server group specified with sgid. If force is set to 1, the server group will be deleted even if there are clients within.

Permissions:

b_virtualserver_servergroup_delete

Syntax:

```
servergroupdel sgid={groupID} force={1|0}
```

Example:

```
servergroupdel sgid=13  
error id=0 msg=ok
```

SERVERGROUPRENAME

Changes the name of the server group specified with `sgid`.

Permissions:

`i_group_modify_power`
`i_group_needed_modify_power`

Syntax:

```
servergrouprename sgid={groupID} name={groupName}
```

Example:

```
servergrouprename cgid=13 name=New\Name  
error id=0 msg=ok
```

SERVERGROUPPERMLIST

Displays a list of permissions assigned to the server group specified with `sgid`.

Permissions:

`b_virtualserver_servergroup_permission_list`

Syntax:

```
servergroupperm list sgid={groupID}
```

Example:

```
servergroupperm list sgid=13  
permid=8470 permvalue=1 permnegated=0 permskip=0|permid=8475 permvalue=1 ...  
error id=0 msg=ok
```

SERVERGROUPADDPERM

Adds a set of specified permissions to the server group specified with `sgid`. Multiple permissions can be added by providing the four parameters of each permission.

Permissions:

`i_group_modify_power`
`i_group_needed_modify_power`
`i_permission_modify_power`

Syntax:

```
servergroupaddperm sgid={groupID} permid={permID}...  
permvalue={permValue}... permnegated={1|0}... permskip={1|0}...
```

Example:

```
servergroupaddperm sgid=13 permid=17276 permvalue=50 permnegated=0 permskip=0|permid=21415  
permvalue=20 permnegated=0  
error id=0 msg=ok
```

SERVERGROUPDELPERM

Removes a set of specified permissions from the server group specified with `sgid`. Multiple permissions can be removed at once.

Permissions:

`i_group_modify_power`
`i_group_needed_modify_power`
`i_permission_modify_power`

Syntax:

```
servergroupdelperm sgid={groupID} permid={permID}...
```

Example:

```
servergroupdelperm sgid=16 permid=17276|permid=21415  
error id=0 msg=ok
```

SERVERGROUPADDCLIENT

Adds a client to the server group specified with `sgid`. Please note that a client cannot be added to default groups or template groups.

Permissions:

`i_group_member_add_power`
`i_group_needed_member_add_power`

Syntax:

```
servergroupaddclient sgid={groupID} cldbid=={clientDBID}
```

Example:

```
servergroupaddclient sgid=16 cldbid=3  
error id=0 msg=ok
```

SERVERGROUPDELCLIENT

Removes a client from the server group specified with `sgid`.

Permissions:

`i_group_member_remove_power`
`i_group_needed_member_remove_power`

Syntax:

```
servergroupdelclient sgid={groupID} cldbid=={clientDBID}
```

Example:

```
servergroupdelclient sgid=16 cldbid=3  
error id=0 msg=ok
```

SERVERGROUPCLIENTLIST

Displays the IDs of all clients currently residing in the server group specified with `sgid`. If you're using the `-names` option, the output will also contain the last known nickname and the unique identifier of the clients.

Permissions:

`b_virtualserver_servergroup_client_list`

Syntax:

```
servergroupclientlist sgid={groupID} [-names]
```

Example:

```
servergroupclientlist sgid=16  
cldbid=7|cldbid=8|cldbid=9|cldbid=11|cldbid=13|cldbid=16|cldbid=18|cldbid=29|cldbid=32|cldbid=34|cldbid=37|cldbid=4  
0|cldbid=47|cldbid=53  
error id=0 msg=ok
```

SERVERGROUPSBYCLIENTID

Displays all server groups the client specified with `cldbid` is currently residing in.

Syntax:

```
servergroupsbyclientid sgid={clientDBID}
```

Example:

```
servergroupsbyclientid cldbid=18  
name=Server\sAdmin sgid=6 cldbid=18  
error id=0 msg=ok
```

SERVERSAPSHOTCREATE

Displays a snapshot of the selected virtual server containing all settings, groups and known client identities.

The data from a server snapshot can be used to restore a virtual servers configuration.

Permissions:

b_virtualserver_snapshot_create

Syntax:

serversnapshotcreate

Example:

```
serversnapshotcreate
hash=bnTd2E1kNITHjYRCFjgbKK05P8=|virtualserver_unique_identifier=zrPkjznB1tMnRwj01xx7RxXjqeY=
virtualserver_name=TeamSpeak\s]I[\sServer ...
error id=0 msg=ok
```

SERVERSAPSHOTDEPLOY

Restores the selected virtual servers configuration using the data from a previously created server snapshot. Please note that the *TeamSpeak 3 Server* does **NOT** check for necessary permissions while deploying a snapshot so the command could be abused to gain additional privileges.

Permissions:

b_virtualserver_snapshot_deploy

Syntax:

serversnapshotdeploy virtualserver_snapshot

Example:

```
serversnapshotdeploy
hash=bnTd2E1kNITHjYRCFjgbKK05P8=|virtualserver_unique_identifier=zrPkjznB1tMnRwj01xx7RxXjq= ... error id=0 msg=ok
```

SERVERNIFYREGISTER

Registers for a specified category of events on a virtual server to receive notification messages. Depending on the notifications you've registered for, the server will send you a message on every event in the view of your *ServerQuery* client (e.g. clients joining your channel, incoming text messages, server configuration changes, etc). The event source is declared by the event parameter while id can be used to limit the notifications to a specific channel.

Permissions:

b_virtualserver_notify_register

Syntax:

servernotifyregister event={server|channel|textserver|textchannel|textprivate} [id={channelID}]

Example:

```
servernotifyregister event=server
error id=0 msg=ok
```

SERVERNIFYUNREGISTER

Unregisters all events previously registered with `servernotifyregister` so you will no longer receive notification messages.

Permissions:

b_virtualserver_notify_unregister

Syntax:

servernotifyunregister

Example:

```
servernotifyunregister
error id=0 msg=ok
```

GM

Sends a text message to all clients on all virtual servers in the *TeamSpeak 3 Server* instance.

Permissions:

b_serverinstance_textmessage_send

Syntax:

```
gm msg={text}
```

Example:

```
gm msg>Hello\sworld!  
error id=0 msg=ok
```

SENDTEXTMESSAGE

Sends a text message a specified target. The type of the target is determined by `targetmode` while `target` specifies the ID of the recipient, whether it be a virtual server, a channel or a client.

For detailed information, see [Definitions](#).

Permissions:

i_client_private_textmessage_power
i_client_needed_private_textmessage_power
b_client_server_textmessage_send
b_client_channel_textmessage_send

Syntax:

```
sendtextmessage targetmode={1-3} target={serverID|channelID|clientID} msg={text}
```

Example:

```
sendtextmessage targetmode=2 target=1 msg>Hello\sworld!  
error id=0 msg=ok
```

LOGVIEW

Displays a specified number of entries from the servers log. Depending on your permissions, you'll receive entries from the server instance log and/or your virtual server log.

Using a combination of the `comparator` and `timestamp` parameters allows you to filter for log entries based on a specific date/time.

Permissions:

b_serverinstance_log_view
b_virtualserver_log_view

Syntax:

```
logview limitcount={1-500} [comparator={<|>|=}] [timestamp=YYYY-MM-DD\shh:mm:ss]
```

Example:

```
logview limitcount=30  
timestamp=1259356318 level=4 channel=Query  
msg=query\sfrom\s87.163.52.195:9\issued:\slogview\slimitcount=30|timestamp=1259356148 ...  
error id=0 msg=ok
```

LOGADD

Writes a custom entry into the servers log. Depending on your permissions, you'll be able to add entries into the server instance log and/or your virtual servers log. The `loglevel` parameter specifies the type of the entry.

For detailed information, see [Definitions](#).

Permissions:

`b_serverinstance_log_add`

`b_virtualserver_log_add`

Syntax:

```
logadd loglevel={1-4} logmsg={text}
```

Example:

```
logvadd loglevel=4 logmsg=Informational\smessage!  
error id=0 msg=ok
```

CHANNELLIST

Displays a list of channels created on a virtual server including their ID, order, name, etc. The output can be modified using several command options.

Permissions:

`b_virtualserver_channel_list`

Syntax:

```
channellist [-topic] [-f1ags] [-voice] [-f1ags]
```

Example:

```
channellist -topic  
cid=15 pid=0 channel_order=0 channel_name=Default\sChannel channel_topic=Default\sChannel\shas\sno\s[b]topic[\\b]  
total_clients=2|cid=16 ...  
error id=0 msg=ok
```

CHANNELINFO

Displays detailed configuration information about a channel including ID, topic, description, etc.

For detailed information, see [Channel Properties](#).

Permissions:

`b_channel_info_view`

Syntax:

```
channelinfo cid={channelID}
```

Example:

```
channelinfo cid=1  
channel_name=Default\sChannel channel_topic=Default\sChannel\shas\sno\s[b]topic[\\b]  
channel_description=This\sis\sthe\sdefault\schannel ...  
error id=0 msg=ok
```

CHANNELFIND

Displays a list of channels matching a given name pattern.

Permissions:

`b_virtualserver_channel_search`

Syntax:

```
channelfind [pattern={channelName}]
```

Example:

```
channelfind pattern=default  
cid=15 channel_name=Default\sChannel  
error id=0 msg=ok
```


CHANNELMOVE

Moves a channel to a new parent channel with the ID `cpid`. If `order` is specified, the channel will be sorted right under the channel with the specified ID. If `order` is set to `0`, the channel will be sorted right below the new parent.

Permissions:

`i_channel_min_depth`
`i_channel_max_depth`
`b_channel_modify_parent`
`b_channel_modify_sortorder`

Syntax:

```
channelmove cid={channelID} cpid={channelParentID} [order={channelSortOrder}]
```

Example:

```
channelmove cid=16 cpid=1 order=0  
error id=0 msg=ok
```

CHANNELCREATE

Creates a new channel using the given properties and displays its ID.

For detailed information, see [Channel Properties](#).

Permissions:

`i_channel_min_depth`
`i_channel_max_depth`
`b_channel_create_child`
`b_channel_create_permanent`
`b_channel_create_semi_permanent`
`b_channel_create_temporary`
`b_channel_create_with_topic`
`b_channel_create_with_description`
`b_channel_create_with_password`
`b_channel_create_modify_with_codec_speex8`
`b_channel_create_modify_with_codec_speex16`
`b_channel_create_modify_with_codec_speex32`
`b_channel_create_modify_with_codec_celtmono48`
`i_channel_create_modify_with_codec_maxquality`
`b_channel_create_with_maxclients`
`b_channel_create_with_maxfamilyclients`
`b_channel_create_with_sortorder`
`b_channel_create_with_default`
`b_channel_create_with_needed_talk_power`

Syntax:

```
channelcreate channel_name={channelName} [channel_properties...]
```

Example:

```
channelcreate channel_name=My\sChannel channel_topic=My\sTopic  
cid=16  
error id=0 msg=ok
```

CHANNELEDIT

Changes a channels configuration using given properties.

For detailed information, see [Channel Properties](#).

Permissions:

`i_channel_min_depth`
`i_channel_max_depth`
`b_channel_modify_parent`

b_channel_modify_make_default
b_channel_modify_make_permanent
b_channel_modify_make_semi_permanent
b_channel_modify_make_temporary
b_channel_modify_name
b_channel_modify_topic
b_channel_modify_description
b_channel_modify_password
b_channel_modify_codec
b_channel_create_modify_with_codec_speex8
b_channel_create_modify_with_codec_speex16
b_channel_create_modify_with_codec_speex32
b_channel_create_modify_with_codec_celtmono48
b_channel_modify_codec_quality
b_channel_create_modify_with_codec_maxquality
b_channel_modify_maxclients
b_channel_modify_maxfamilyclients
b_channel_modify_sortorder
b_channel_modify_needed_talk_power
i_channel_modify_power
i_channel_needed_modify_power

Syntax:

```
channeledit cid={channelID} [channel_properties...]
```

Example:

```
channeledit cid=15 channel_codec_quality=3 channel_description=My\Description  
error id=0 msg=ok
```

CHANNELDELETE

Deletes an existing channel by ID. If force is set to 1, the channel will be deleted even if there are clients within.

Permissions:

b_channel_delete_permanent
b_channel_delete_semi_permanent
b_channel_delete_temporary
b_channel_delete_flag_force

Syntax:

```
channeldelete cid={channelID} force={1|0}
```

Example:

```
channeldelete cid=16 force=1  
error id=0 msg=ok
```

CHANNELPERMLIST

Displays a list of permissions defined for a channel.

Permissions:

b_virtualserver_channel_permission_list

Syntax:

```
channelpermlist cid={channelID}
```

Example:

```
channelpermlist cid=2  
cid=2 permid=4353 permvalue=1 permnegated=0 permskip=0|permid=17276 permvalue=50 ...  
error id=0 msg=ok
```

CHANNELADDPERM

Adds a set of specified permissions to a channel. Multiple permissions can be added by providing the two parameters of each permission.

Permissions:

i_group_modify_power
i_group_needed_modify_power
i_permission_modify_power

Syntax:

```
channeladdperm cid={channelID} permid={permID}... permvalue={permValue}...
```

Example:

```
channeladdperm cid=16 permid=17276 permvalue=50|permid=21415 permvalue=20  
error id=0 msg=ok
```

CHANNELDELPERM

Removes a set of specified permissions from a channel. Multiple permissions can be removed at once.

Permissions:

i_group_modify_power
i_group_needed_modify_power
i_permission_modify_power

Syntax:

```
channeldelperm cid=123 permid={permID}...
```

Example:

```
channeldelperm cid=16 permid=17276|permid=21415  
error id=0 msg=ok
```

CHANNELGROUPLIST

Displays a list of channel groups available on the selected virtual server.

Permissions:

b_virtualserver_channelgroup_list

Syntax:

```
channelgroupelist
```

Example:

```
channelgroupelist  
cgid=1 name=Channel\sAdmin type=2 iconid=100 savedb=1|cgid=2 ...  
error id=0 msg=ok
```

CHANNELGROUPADD

Creates a new channel group using a given name and displays its ID.

Permissions:

b_virtualserver_channelgroup_create

Syntax:

```
channelgroupadd name={groupName}
```

Example:

```
channelgroupadd name=Channel\sAdmin  
cgid=13  
error id=0 msg=ok
```

CHANNELGROUPDEL

Deletes a channel group by ID. If *force* is set to *1*, the channel group will be deleted even if there are clients within.

Permissions:

b_virtualserver_channelgroup_delete

Syntax:

```
channelgroupdel cgid={groupID} force={1|0}
```

Example:

```
channelgroupdel cgid=13  
error id=0 msg=ok
```

CHANNELGROUPRENAME

Changes the name of a specified channel group.

Permissions:

i_group_modify_power
i_group_needed_modify_power

Syntax:

```
channelgrouprename cgid={groupID} name={groupName}
```

Example:

```
channelgrouprename cgid=13 name=New\sName  
error id=0 msg=ok
```

CHANNELGROUPADDPERM

Adds a set of specified permissions to a channel group. Multiple permissions can be added by providing the two parameters of each permission.

Permissions:

i_group_modify_power
i_group_needed_modify_power
i_permission_modify_power

Syntax:

```
channelgroupaddperm cgid={groupID} permid={permID}... permvalue={permValue}...
```

Example:

```
channelgroupaddperm cgid=13 permid=17276 permvalue=50|permid=21415 permvalue=20  
error id=0 msg=ok
```

CHANNELDELPERM

Removes a set of specified permissions from the channel group. Multiple permissions can be removed at once.

Permissions:

i_group_modify_power
i_group_needed_modify_power
i_permission_modify_power

Syntax:

```
channelgroupdelperm cgid={groupID} permid={permID}...
```

Example:

```
channelgroupdelperm cgid=16 permid=17276|permid=21415  
error id=0 msg=ok
```

CHANNELGROUPPERMLIST

Displays a list of permissions assigned to the channel group specified with `cgid`.

Permissions:

`b_virtualserver_channelgroup_permission_list`

Syntax:

```
channelgrouppermlist cgid={groupID}
```

Example:

```
channelgrouppermlist cgid=13
  permid=8470 permvalue=1 permnegated=0 permskip=0|permid=8475 permvalue=1 ...
  error id=0 msg=ok
```

CHANNELGROUPCLIENTLIST

Displays all the client and/or channel IDs currently assigned to channel groups. All three parameters are optional so you're free to choose the most suitable combination for your requirements.

Permissions:

`b_virtualserver_channelgroup_client_list`

Syntax:

```
channelgroupclientlist [cid={channelID}] [clid={clientID}] [cgid={groupID}]
```

Example:

```
channelgroupclientlist cid=2 cgid=9
  cid=2 cldbid=9 cgid=9|cid=2 cldbid=24 cgid=9|cid=2 cldbid=47 cgid=9
  error id=0 msg=ok
```

SETCLIENTCHANNELGROUP

Sets the channel group of a client to the ID specified with `cgid`.

Permissions:

`i_group_member_add_power`
`i_group_needed_member_add_power`
`i_group_member_remove_power`
`i_group_needed_member_remove_power`

Syntax:

```
setclientchannelgroup cgid={groupID} cid={channelID} cldbid={clientDBID}
```

Example:

```
setclientchannelgroup cgid=13 cid=15 cldbid=20
  error id=0 msg=ok
```

CLIENTLIST

Displays a list of clients online on a virtual server including their ID, nickname, status flags, etc. The output can be modified using several command options. Please note that the output will only contain clients which are currently in channels you're able to subscribe to.

Permissions:

`b_virtualserver_client_list`

Syntax:

```
clientlist [-uid] [-away] [-voice] [-groups]
```

Example:

```
clientlist -away
  clid=5 cid=7 client_database_id=40 client_nickname=ScP client_type=0 client_away=1
  client_away_message=not\shere|clid=6 ...
  error id=0 msg=ok
```

CLIENTINFO

Displays detailed configuration information about a client including unique ID, nickname, client version, etc.

Permissions:

b_client_info_view

Syntax:

```
clientinfo clid={clientID}
```

Example:

```
clientinfo cid=6
client_unique_identifier=P5H2hrN6+gpQI4n\dxp3p17vtY0= client_nickname=Rabe85 client_version=3.0.0-
alpha24\s[Build:\s8785]\s(UI:\s8785) ...
error id=0 msg=ok
```

CLIENTFIND

Displays a list of clients matching a given name pattern.

Permissions:

b_virtualserver_client_search

Syntax:

```
clientfind pattern={clientName}
```

Example:

```
clientfind pattern=sven
clid=7 client_nickname=Sven
error id=0 msg=ok
```

CLIENTEDIT

Changes a clients settings using given properties.

For detailed information, see [Client Properties](#).

Permissions:

b_client_modify_description

b_client_set_talk_power

Syntax:

```
clientedit clid={clientID} [client_properties...]
```

Example:

```
clientedit clid=10 client_description=Best\sguy\sever!
error id=0 msg=ok
```

CLIENTDBLIST

Displays a list of client identities known by the server including their database ID, last nickname, etc.

Permissions:

b_virtualserver_client_dblist

Syntax:

```
clientdblist
```

Example:

```
clientdblist
cldbid=7 client_unique_identifier=DZhdQU58qyooEK4Fr8Ly738hEmc= client_nickname=MuhChy client_created=1259147468
client_lastconnected=1259421233 error id=0 msg=ok
```

CLIENTDBFIND

Displays a list of client database IDs matching a given pattern. You can either search for a clients last known nickname or his unique identity by using the `-uid` option.

Permissions:

`b_virtualserver_client_dbsearch`

Syntax:

```
clientdbfind pattern={clientName|clientUID} [-uid]
```

Example:

```
clientdbfind pattern=sven
cldbid=56
error id=0 msg=ok
```

CLIENTDBEDIT

Changes a clients settings using given properties.

For detailed information, see [Client Properties](#).

Permissions:

`b_client_modify_dbproperties`

`b_client_modify_description`

`b_client_set_talk_power`

Syntax:

```
clientdbedit cldbldid={clientDBID} [client_properties..]
```

Example:

```
clientdbedit cldbldid=56 client_description=Best\sguy\sever!
error id=0 msg=ok
```

CLIENTDBDELETE

Deletes a clients properties from the database.

Permissions:

`b_client_delete_dbproperties`

Syntax:

```
clientdbdelete cldbldid={clientDBID}
```

Example:

```
clientdbdelete cldbldid=56
error id=0 msg=ok
```

CLIENTGETIDS

Displays all client IDs matching the unique identifier specified by `cluid`.

Syntax:

```
clientgetids cluid={clientUID}
```

Example:

```
clientgetids cluid=dyjxkshZP6bz0n3bnwFQ1CkwZOM=
cluid=dyjxkshZP6bz0n3bnwFQ1CkwZOM= clid=1 name=Janko
error id=0 msg=ok
```

CLIENTGETDBIDFROMUID

Displays the database ID matching the unique identifier specified by `cluid`.

Syntax:

```
clientgetdbidfromuid cluid={clientUID}
```

Example:

```
clientgetdbidfromuid cluid=djyxkshZP6bz0n3bnwFQ1CkwZOM=  
cluid=djyxkshZP6bz0n3bnwFQ1CkwZOM= cldbid=32  
error id=0 msg=ok
```

CLIENTGETNAMEFROMUID

Displays the database ID and nickname matching the unique identifier specified by `cluid`.

Syntax:

```
clientgetnamefromuid cluid={clientUID}
```

Example:

```
clientgetnamefromuid cluid=djyxkshZP6bz0n3bnwFQ1CkwZOM=  
cluid=djyxkshZP6bz0n3bnwFQ1CkwZOM= cldbid=32 name=Janko  
error id=0 msg=ok
```

CLIENTGETNAMEFROMDBID

Displays the unique identifier and nickname matching the database ID specified by `cldbid`.

Syntax:

```
clientgetnamefromdbid cldbid={clientDBID}
```

Example:

```
clientgetnamefromdbid cldbid=32  
cluid=djyxkshZP6bz0n3bnwFQ1CkwZOM= cldbid=32 name=Janko  
error id=0 msg=ok
```

CLIENTSETSERVERQUERYLOGIN

Updates your own *ServerQuery* login credentials using a specified username. The password will be auto-generated.

Permissions:

```
b_client_create_modify_serverquery_login
```

Syntax:

```
clientsetserverquerylogin client_login_name={username}
```

Example:

```
clientsetserverquerylogin client_login_name=admin  
client_login_password=+r\TQqvR  
error id=0 msg=ok
```

CLIENTUPDATE

Change your ServerQuery clients settings using given properties.

For detailed information, see [Client Properties](#).

Syntax:

```
clientupdate [client_properties...]
```

Example:

```
clientupdate client_nickname=ScP\s(query)  
error id=0 msg=ok
```


CLIENTMOVE

Moves one or more clients specified with `clid` to the channel with ID `cid`. If the target channel has a password, it needs to be specified with `cpw`. If the channel has no password, the parameter can be omitted.

Permissions:

`i_client_move_power`
`i_client_needed_move_power`

Syntax:

```
clientmove clid={clientID}... cid={channelID} [cpw={channelPassword}]
```

Example:

```
clientmove clid=5|clid=6 cid=3  
error id=0 msg=ok
```

CLIENTKICK

Kicks one or more clients specified with `clid` from their currently joined channel or from the server, depending on `reasonid`. The `reasonmsg` parameter specifies a text message sent to the kicked clients. This parameter is optional and may only have a maximum of 40 characters.

For detailed information, see [Definitions](#).

Permissions:

`i_client_kick_power`
`i_client_needed_kick_power`

Syntax:

```
clientkick clid={clientID}... reasonid={4|5} [reasonmsg={text}]
```

Example:

```
clientkick clid=5|clid=6 reasonid=4 reasonmsg=Go\sway!  
error id=0 msg=ok
```

CLIENTPOKE

Sends a poke message to the client specified with `clid`.

Permissions:

`i_client_poke_power`
`i_client_needed_poke_power`

Syntax:

```
clientpoke clid={clientID}... msg={text}
```

Example:

```
clientpoke clid=5 msg=Wake\sup!  
error id=0 msg=ok
```

CLIENTPERMLIST

Displays a list of permissions defined for a client.

Permissions:

`b_virtualserver_client_permission_list`

Syntax:

```
clientpermlist cldbid={clientDBID}
```

Example:

```
clientpermlist cldbid=2  
cldbid=2 permid=4353 permvalue=1 permnegated=0 permskip=0|permid=17276 permvalue=50 permnegated=0  
permskip=0|permid=21415 ...  
error id=0 msg=ok
```

CLIENTADDPERM

Adds a set of specified permissions to a client. Multiple permissions can be added by providing the three parameters of each permission.

Permissions:

i_group_modify_power
i_group_needed_modify_power
i_permission_modify_power

Syntax:

```
clientaddperm cldbldid={clientDBID} permid={permID}...  
permvalue={permValue}... permkip={1|0}...
```

Example:

```
clientaddperm cldbldid=16 permid=17276 permvalue=50 permkip=1|permid=21415 permvalue=20 permkip=0  
error id=0 msg=ok
```

CLIENTDELPERM

Removes a set of specified permissions from a client. Multiple permissions can be removed at once.

Permissions:

i_group_modify_power
i_group_needed_modify_power
i_permission_modify_power

Syntax:

```
channeldelperm cldbldid={clientDBID} permid={permID}...
```

Example:

```
clientdelperm cldbldid=16 permid=17276|permid=21415  
error id=0 msg=ok
```

CHANNELCLIENTPERMLIST

Displays a list of permissions defined for a client in a specific channel.

Permissions:

b_virtualserver_channelclient_permission_list

Syntax:

```
channelclientpermlist cid={channelID} cldbldid={clientDBID}
```

Example:

```
channelclientpermlist cid=12 cldbldid=3  
cid=12 cldbldid=3 permid=4353 permvalue=1 permnegated=0 permkip=0|permid=17276 permvalue=50 permnegated=0  
permkip=0|permid=21415 ...  
error id=0 msg=ok
```

CHANNELCLIENTADDPERM

Adds a set of specified permissions to a client in a specific channel. Multiple permissions can be added by providing the three parameters of each permission.

Permissions:

i_group_modify_power
i_group_needed_modify_power
i_permission_modify_power

Syntax:

```
channelclientaddperm cid={channelID} cldbldid={clientDBID} permid={permID}...  
permvalue={permValue}...
```

Example:

```
channelclientaddperm cid=12 cldbldid=3 permid=17276 permvalue=50|permid=21415 permvalue=20  
error id=0 msg=ok
```

CHANNELCLIENTDELPERM

Removes a set of specified permissions from a client in a specific channel. Multiple permissions can be removed at once.

Permissions:

i_group_modify_power
i_group_needed_modify_power
i_permission_modify_power

Syntax:

```
channelclientdelperm cid={channelID} cldbld={clientDBID} permid={permID}...
```

Example:

```
channelclientdelperm cid=12 cldbld=3 permid=17276|permid=21415  
error id=0 msg=ok
```

PERMISSIONLIST

Displays a list of permissions available on the server instance including ID, name and description.

Permissions:

b_serverinstance_permission_list

Syntax:

```
permissionlist
```

Example:

```
permissionlist  
permid=21413 permname=b_client_channel_textmessage_send permdesc=Send\stext\smessages\sto\schannel|permid=21414  
permname=i_client_talk_power ...  
error id=0 msg=ok
```

PERMOVERVIEW

Displays all permissions assigned to a client for the channel specified with cid. If permid is set to 0, all permissions will be displayed.

Permissions:

b_client_permissionoverview_view

Syntax:

```
permooverview cid={channelID} cldbld={clientDBID} permid={permID}
```

Example:

```
permooverview cldbld=57 cid=74 permid=0  
t=0 id1=5 id2=0 p=37 v=1 n=0 s=0|t=0 id1=5 id2=0 p=38 v=1 n=0 s=0 ...  
error id=0 msg=ok
```

PERMFIND

Displays the IDs of all clients, channels or groups using the permission specified with permid.

Permissions:

b_virtualserver_permission_find
b_serverinstance_permission_find

Syntax:

```
permfind permid={permID}
```

Example:

```
permfind permid=4353  
t=0 id1=1 id2=0 p=4353|t=0 id1=2 id2=0 p=4353  
error id=0 msg=ok
```

TOKENLIST

Displays a list of tokens available including their type and group IDs. Tokens can be used to gain access to specified server or channel groups.

Permissions:

b_virtualserver_token_list

Syntax:

tokenlist

Example:

```
tokenlist
token=88CVUg\zkujt+y+WfHdko79UcM4R6uyCL6nEfy3B token_type=0 token_id1=9 token_id2=0 ...
error id=0 msg=ok
```

TOKENADD

Create a new token. If tokentype is set to 0, the ID specified with tokenid1 will be a server group ID. Otherwise, tokenid1 is used as a channel group ID and you need to provide a valid channel ID using tokenid2.

Permissions:

b_virtualserver_token_add

Syntax:

tokenadd tokentype={1|0} tokenid1={groupID} tokenid2={channelID}

Example:

```
tokenadd tokentype=0 tokenid1=6 tokenid2=0
token=eKnFZQ9EK7G7MhtuQB6+N2B1PNZZ60ZL3ycDp20W
error id=0 msg=ok
```

TOKENDELETE

Deletes an existing token matching the token key specified with token.

Permissions:

b_virtualserver_token_delete

Syntax:

tokendelete token={tokenKey}

Example:

```
tokendelete token=eKnFZQ9EK7G7MhtuQB6+N2B1PNZZ60ZL3ycDp20W
error id=0 msg=ok
```

TOKENUSE

Use a token key gain access to a server or channel group. Please note that the server will automatically delete the token after it has been used.

Permissions:

b_virtualserver_token_use

Syntax:

tokenuse token={tokenKey}

Example:

```
tokenuse token=eKnFZQ9EK7G7MhtuQB6+N2B1PNZZ60ZL3ycDp20W
error id=0 msg=ok
```

MESSAGELIST

Displays a list of offline messages you've received. The output contains the senders unique identifier, the messages subject, etc.

Syntax:

```
messagelist
```

Example:

```
messagelist
msgid=4 cluid=xwEzb5EN0ag1VHu9oe1K++reUyE= subject=Test timestamp=1259439465 flag_read=0 ...
error id=0 msg=ok
```

MESSAGEADD

Sends an offline message to the client specified by `cluid`.

Syntax:

```
messageadd cluid={clientUID} subject={subject} message={text}
```

Example:

```
messageadd cluid=oHhi9WzXLNEFQ0wAu4JYKGU+C+c= subject=Hi! message=Where\aaare\you?!?
error id=0 msg=ok
```

MESSAGEGET

Displays an existing offline message with ID `msgid` from your inbox. Please note that this does not automatically set the `flag_read` property of the message.

Syntax:

```
messageget msgid={messageID}
```

Example:

```
messageget msgid=4
msgid=4 cluid=xwEzb5EN0ag1VHu9oe1K++reUyE= subject=Hi! message=Where\aaare\you?!?
error id=0 msg=ok
```

MESSAGEUPDATEFLAG

Updates the `flag_read` property of the offline message specified with `msgid`. If `flag` is set to `1`, the message will be marked as read.

Syntax:

```
messageupdateflag msgid={messageID} flag={1|0}
```

Example:

```
messageupdateflag msgid=4 flag=1
error id=0 msg=ok
```

MESSAGEDEL

Deletes an existing offline message with ID `msgid` from your inbox.

Syntax:

```
messagedel msgid={messageID}
```

Example:

```
messagedel msgid=4
error id=0 msg=ok
```

COMPLAINLIST

Displays a list of complaints on the selected virtual server. If `tcldb`id is specified, only complaints about the targeted client will be shown.

Permissions:

`b_client_complain_list`

Syntax:

```
complainlist [tcldb={targetClientDBID}]
```

Example:

```
complainlist tcldb=3
  tcldb=3 tname=Julian fcldb=56 fname=Sven message=Bad\sguy! timestamp=1259440948 ...
  error id=0 msg=ok
```

COMPLAINADD

Submits a complaint about the client with database ID `tcldb`id to the server.

Permissions:

`i_client_complain_power`

`i_client_needed_complain_power`

Syntax:

```
complainadd tcldb={targetClientDBID} message={text}
```

Example:

```
complainadd tcldb=3 message=Bad\sguy!
  error id=0 msg=ok
```

COMPLAINDEL

Deletes the complaint about the client with ID `tcldb`id submitted by the client with ID `fcldb`id from the server.

Permissions:

`b_client_complain_delete`

`b_client_complain_delete_own`

Syntax:

```
complaindel tcldb={targetClientDBID} fcldb={fromClientDBID}
```

Example:

```
complaindel tcldb=3 fcldb=4
  error id=0 msg=ok
```

COMPLAINDELALL

Deletes all complaints about the client with database ID `tcldb`id from the server.

Permissions:

`b_client_complain_delete`

Syntax:

```
complaindelall tcldb={targetClientDBID}
```

Example:

```
complaindelall tcldb=3
  error id=0 msg=ok
```

BANCLIENT

Bans the client specified with ID `clid` from the server.

Permissions:

`i_client_ban_power`
`i_client_needed_ban_power`

Syntax:

```
banclient clid={clientID} [time={timeInSeconds}] [banreason={text}]
```

Example:

```
banclient clid=4 time=3600  
error id=0 msg=ok
```

BANLIST

Displays a list of active bans on the selected virtual server.

Permissions:

`b_client_ban_list`

Syntax:

```
banlist
```

Example:

```
banlist  
banid=7 ip=1.2.3.4 created=1259444002242 invokename=Sven invokercldbid=56 invokeruid=oHhi9WzXLNEFQ0wAu4JYKGU+C+c=  
reason enforcements=0  
error id=0 msg=ok
```

BANADD

Adds a new ban rule on the selected virtual server. All parameters are optional but at least one of the following must be set: `ip`, `name`, or `uid`.

Permissions:

`b_client_ban_create`

Syntax:

```
banadd [ip={regex}] [name={regex}] [uid={clientUID}]  
[time={timeInSeconds}] [banreason={text}]
```

Example:

```
banadd ip=1.2.3.4 banreason=just\s4\sfun  
error id=0 msg=ok
```

BANDEL

Deletes the ban rule with ID `banid` from the server.

Permissions:

`b_client_ban_delete`
`b_client_ban_delete_own`

Syntax:

```
bandel banid={banID}
```

Example:

```
bandel banid=3  
error id=0 msg=ok
```

BANDELALL

Deletes all active ban rules from the server.

Permissions:

b_client_ban_delete

Syntax:

```
bande1a11
```

Example:

```
bande1a11
error id=0 msg=ok
```

FTINITUPLOAD

Initializes a file transfer upload. `clientftfid` is an arbitrary ID to identify the file transfer on client-side.

On success, the server generates a new `ftkey` which is required to start uploading the file through *TeamSpeak 3's* file transfer interface.

Permissions:

i_ft_file_upload_power
i_ft_needed_file_upload_power
i_ft_quota_mb_upload_per_client

Syntax:

```
ftinitupload clientftfid={clientFileTransferID} name={filePath} cid={channelID}
cpw={channelPassword} size={fileSize} overwrite={1|0} resume={1|0}
```

Example:

```
ftinitupload clientftfid=1 name=\\image.iso cid=5 cpw= size=673460224 overwrite=1 resume=0
clientftfid=1 serverftfid=6 ftkey=itRNdsIOvcBiBg\\Xj4Ge5lZSrsShHuid port=30033 seekpos=0
error id=0 msg=ok
```

FTINITDOWNLOAD

Initializes a file transfer download. `clientftfid` is an arbitrary ID to identify the file transfer on client-side.

On success, the server generates a new `ftkey` which is required to start downloading the file through *TeamSpeak 3's* file transfer interface.

Permissions:

i_ft_file_download_power
i_ft_needed_file_download_power
i_ft_quota_mb_download_per_client

Syntax:

```
ftinitdownload clientftfid={clientFileTransferID} name={filePath} cid={channelID}
cpw={channelPassword} seekpos={seekPosition}
```

Example:

```
ftinitdownload clientftfid=1 name=\\image.iso cid=5 cpw= seekpos=0
clientftfid=1 serverftfid=7 ftkey=Nr0ga\\4d2GpYC5oKgxcu1T037X83ca\\1 port=30033 size=673460224
error id=0 msg=ok
```


FTLIST

Displays a list of running file transfers on the selected virtual server. The output contains the path to which a file is uploaded to, the current transfer rate in bytes per second, etc.

Permissions:

b_ft_transfer_list

Syntax:

ftlist

Example:

```
ftlist
clid=2 path=files\virtualserver_1\channel_5 name=image.iso size=673460224 sizedone=450756 clientftfid=2
serverftfid=6 sender=0 status=1 current_speed=60872.8 ...
error id=0 msg=ok
```

FTGETFILELIST

Displays a list of files and directories stored in the specified channels file repository.

Permissions:

i_ft_file_browse_power

i_ft_needed_file_browse_power

Syntax:

ftgetfilelist cid={channelID} cpw={channelPassword} path={filePath}

Example:

```
ftgetfilelist cid=2 cpw= path=\
cid=2 path=\ name=Stuff size=0 datetime=1259415210 type=0|name=Pic1.PNG size=563783 datetime=1259425462
type=1|name=Pic2.PNG ...
error id=0 msg=ok
```

FTGETFILEINFO

Displays detailed information about one or more specified files stored in a channels file repository.

Permissions:

i_ft_file_browse_power

i_ft_needed_file_browse_power

Syntax:

ftgetfileinfo cid={channelID} cpw={channelPassword} name={filePath}...

Example:

```
ftgetfileinfo cid=2 cpw= path=\Pic1.PNG|cid=2 cpw= path=\Pic2.PNG
cid=2 path=\ name=Stuff size=0 datetime=1259415210 type=0|name=Pic1.PNG size=563783 datetime=1259425462
type=1|name=Pic2.PNG ...
error id=0 msg=ok
```

FTSTOP

Stops the running file transfer with server-side ID serverftfid.

Syntax:

ftstop serverftfid={serverFileTransferID} delete={1|0}

Example:

```
ftstop serverftfid=2 delete=1
error id=0 msg=ok
```

FTDELETEFILE

Deletes one or more files stored in a channels file repository.

Permissions:

i_ft_file_delete_power
i_ft_needed_file_delete_power

Syntax:

```
ftdeletefile cid={channelID} cpw={channelPassword} name={filePath}...
```

Example:

```
ftdeletefile cid=2 cpw= name=\/Pic1.PNG|name=\/Pic2.PNG  
error id=0 msg=ok
```

FTCREATEDIR

Creates new directory in a channels file repository.

Permissions:

i_ft_directory_create_power
i_ft_needed_file_directory_create_power

Syntax:

```
ftcreatedir cid={channelID} cpw={channelPassword} dirname={dirPath}
```

Example:

```
ftcreatedir cid=2 cpw= dirname=\/My\sDirectory  
error id=0 msg=ok
```

FTRENAMEFILE

Renames a file in a channels file repository. If the two parameters tcid and tcpw are specified, the file will be moved into another channels file repository.

Permissions:

i_ft_file_rename_power
i_ft_needed_file_rename_power

Syntax:

```
ftrenamefile cid={channelID} cpw={channelPassword} [tcid={targetChannelID}]  
[tcpw={targetChannelPassword}] oldname={oldFilePath} newname={newFilePath}
```

Example:

```
ftrenamefile cid=2 cpw= tcid=3 tcpw=secret oldname=\/Pic3.PNG newname=\/Pic3.PNG  
error id=0 msg=ok
```

WHOAMI

Displays information about your current *ServerQuery* connection including the ID of the selected virtual server, your loginname, etc.

Syntax:

```
whoami
```

Example:

```
whoami  
virtualserver_status=online virtualserver_id=1 virtualserver_unique_identifier=zrPkjznB1tMnRwj01xx7RxXjqeY=  
client_channel_id=2 ...  
error id=0 msg=ok
```

SERVER INSTANCE PROPERTIES

This is a list of properties available for the server instance:

NAME	CHANGABLE
INSTANCE_UPTIME <i>Uptime in seconds</i>	No
HOST_TIMESTAMP_UTC <i>Current server date and time as UTC timestamp</i>	No
VIRTUALSERVERS_RUNNING_TOTAL <i>Number of virtual servers running</i>	No
CONNECTION_FILETRANSFER_BANDWIDTH_SENT <i>Current bandwidth used for outgoing file transfers (Bytes/s)</i>	No
CONNECTION_FILETRANSFER_BANDWIDTH_RECEIVED <i>Current bandwidth used for incoming file transfers (Bytes/s)</i>	No
CONNECTION_PACKETS_SENT_TOTAL <i>Total amount of packets sent</i>	No
CONNECTION_PACKETS_RECEIVED_TOTAL <i>Total amount of packets received</i>	No
CONNECTION_BYTES_SENT_TOTAL <i>Total amount of bytes sent</i>	No
CONNECTION_BYTES_RECEIVED_TOTAL <i>Total amount of bytes received</i>	No
CONNECTION_BANDWIDTH_SENT_LAST_SECOND_TOTAL <i>Average bandwidth used for outgoing data in the last second (Bytes/s)</i>	No
CONNECTION_BANDWIDTH_RECEIVED_LAST_SECOND_TOTAL <i>Average bandwidth used for incoming data in the last second (Bytes/s)</i>	No
CONNECTION_BANDWIDTH_SENT_LAST_MINUTE_TOTAL <i>Average bandwidth used for outgoing data in the last minute (Bytes/s)</i>	No
CONNECTION_BANDWIDTH_RECEIVED_LAST_MINUTE_TOTAL <i>Average bandwidth used for incoming data in the last minute (Bytes/s)</i>	No
SERVERINSTANCE_DATABASE_VERSION <i>Database revision number</i>	No
SERVERINSTANCE_GUEST_SERVERQUERY_GROUP <i>Default ServerQuery group ID</i>	Yes
SERVERINSTANCE_TEMPLATE_SERVERADMIN_GROUP <i>Default template group ID for administrators on new virtual servers (used to create initial token)</i>	Yes
SERVERINSTANCE_FILETRANSFER_PORT <i>TCP port used for file transfers</i>	Yes
SERVERINSTANCE_MAX_DOWNLOAD_TOTAL_BANDWITDH <i>Max bandwidth available for outgoing file transfers (Bytes/s)</i>	Yes
SERVERINSTANCE_MAX_UPLOAD_TOTAL_BANDWITDH <i>Max bandwidth available for incoming file transfers (Bytes/s)</i>	Yes

VIRTUAL SERVER PROPERTIES

This is a list of properties available for virtual servers:

NAME	CHANGABLE
VIRTUALSERVER_NAME <i>Name of the virtual server</i>	Yes
VIRTUALSERVER_WELCOMEMESSAGE <i>Welcome message of the virtual server</i>	Yes
VIRTUALSERVER_MAXCLIENTS <i>Number of slots available on the virtual server</i>	Yes
VIRTUALSERVER_PASSWORD <i>Password of the virtual server</i>	Yes
VIRTUALSERVER_FLAG_PASSWORD <i>Indicates whether the server has a password set or not</i>	Yes
VIRTUALSERVER_CLIENTSONLINE <i>Number of clients connected to the virtual server</i>	No
VIRTUALSERVER_QUERYCLIENTS_ONLINE <i>Number of ServerQuery clients connected to the virtual server</i>	No
VIRTUALSERVER_CHANNELSONLINE <i>Number of channels created on the virtual server</i>	No
VIRTUALSERVER_CREATED <i>Creation date and time of the virtual server as UTC timestamp</i>	No
VIRTUALSERVER_UPTIME <i>Uptime in seconds</i>	No
VIRTUALSERVER_HOSTMESSAGE <i>Host message of the virtual server</i>	Yes
VIRTUALSERVER_HOSTMESSAGE_MODE <i>Host message mode of the virtual server (see Definitions)</i>	Yes
VIRTUALSERVER_DEFAULT_SERVER_GROUP <i>Default server group ID</i>	Yes
VIRTUALSERVER_DEFAULT_CHANNEL_GROUP <i>Default channel group ID</i>	Yes
VIRTUALSERVER_DEFAULT_CHANNEL_ADMIN_GROUP <i>Default channel administrator group ID</i>	Yes
VIRTUALSERVER_PLATFORM <i>Operating system the server is running on</i>	No
VIRTUALSERVER_VERSION <i>Server version information including build number</i>	No
VIRTUALSERVER_MAX_DOWNLOAD_TRANSFERS_TOTAL <i>Max number of outgoing file transfers for the virtual server</i>	Yes
VIRTUALSERVER_MAX_DOWNLOAD_TRANSFERS_INDIVIDUAL <i>Max number of outgoing file transfers per client on the virtual server</i>	Yes
VIRTUALSERVER_MAX_UPLOAD_TRANSFERS_TOTAL <i>Max number of outgoing file transfers for the virtual server</i>	Yes
VIRTUALSERVER_MAX_UPLOAD_TRANSFERS_INDIVIDUAL <i>Max number of outgoing file transfers per client on the virtual server</i>	Yes
VIRTUALSERVER_MAX_DOWNLOAD_TOTAL_BANDWIDTH <i>Max bandwidth for outgoing file transfers on the virtual server (Bytes/s)</i>	Yes
VIRTUALSERVER_MAX_UPLOAD_TOTAL_BANDWIDTH <i>Max bandwidth for incoming file transfers on the virtual server (Bytes/s)</i>	Yes
VIRTUALSERVER_MAX_DOWNLOAD_INDIVIDUAL_BANDWIDTH <i>Max bandwidth for outgoing file transfers per client on the virtual server (Bytes/s)</i>	Yes
VIRTUALSERVER_MAX_UPLOAD_INDIVIDUAL_BANDWIDTH <i>Max bandwidth for incoming file transfers per client on the virtual server (Bytes/s)</i>	Yes
VIRTUALSERVER_HOSTBANNER_URL <i>Host banner URL opened on click</i>	Yes
VIRTUALSERVER_HOSTBANNER_GFX_URL <i>Host banner URL used as image source</i>	Yes
VIRTUALSERVER_HOSTBANNER_GFX_INTERVAL <i>Interval for reloading the banner on client-side</i>	Yes

NAME	CHANGABLE
VIRTUALSERVER_COMPLAIN_AUTOBAN_COUNT <i>Number of complaints needed to ban a client automatically</i>	Yes
VIRTUALSERVER_COMPLAIN_AUTOBAN_TIME <i>Time in seconds used for automatic bans triggered by complaints</i>	Yes
VIRTUALSERVER_COMPLAIN_REMOVE_TIME <i>Time in seconds before a complaint is deleted automatically</i>	Yes
VIRTUALSERVER_MIN_CLIENTS_IN_CHANNEL_BEFORE_FORCED_SILENCE <i>Number of clients in the same channel needed to force silence</i>	Yes
VIRTUALSERVER_PRIORITY_SPEAKER_DIMM_MODIFICATOR <i>Client volume lowered automatically while a priority speaker is talking</i>	Yes
VIRTUALSERVER_ANTIFLOOD_POINTS_TICK_REDUCE <i>Anti-flood points removed from a client for being good</i>	Yes
VIRTUALSERVER_ANTIFLOOD_POINTS_NEEDED_WARNING <i>Anti-flood points needed to receive a warning message from the server</i>	Yes
VIRTUALSERVER_ANTIFLOOD_POINTS_NEEDED_KICK <i>Anti-flood points needed to be kicked from the server</i>	Yes
VIRTUALSERVER_ANTIFLOOD_POINTS_NEEDED_BAN <i>Anti-flood points needed to be banned from the server</i>	Yes
VIRTUALSERVER_ANTIFLOOD_POINTS_NEEDED_BAN_TIME <i>Time in seconds used for automatic bans triggered by the flood protection</i>	Yes
VIRTUALSERVER_CLIENT_CONNECTIONS <i>Total number of clients connected to the virtual server since it was last started</i>	No
VIRTUALSERVER_QUERY_CLIENT_CONNECTIONS <i>Total number of ServerQuery clients connected to the virtual server since it was last started</i>	No
VIRTUALSERVER_HOSTBUTTON_TOOLTIP <i>Text used for the tooltip of the host button on client-side</i>	Yes
VIRTUALSERVER_HOSTBUTTON_URL <i>URL opened on click on the host button</i>	Yes
VIRTUALSERVER_DOWNLOAD_QUOTA <i>Download quota for the virtual server (MByte)</i>	Yes
VIRTUALSERVER_UPLOAD_QUOTA <i>Download quota for the virtual server (MByte)</i>	Yes
VIRTUALSERVER_MONTH_BYTES_DOWNLOADED <i>Number of bytes downloaded from the virtual server on the current month</i>	No
VIRTUALSERVER_MONTH_BYTES_UPLOADED <i>Number of bytes uploaded to the virtual server on the current month</i>	No
VIRTUALSERVER_TOTAL_BYTES_DOWNLOADED <i>Number of bytes downloaded from the virtual server since it was last started</i>	No
VIRTUALSERVER_TOTAL_BYTES_UPLOADED <i>Number of bytes uploaded to the virtual server since it was last started</i>	No
VIRTUALSERVER_UNIQUE_IDENTIFER <i>Unique ID of the virtual server</i>	No
VIRTUALSERVER_ID <i>Database ID of the virtual server</i>	No
VIRTUALSERVER_MACHINE_ID <i>Machine ID of the virtual server identifying the server instance</i>	Yes
VIRTUALSERVER_PORT <i>UDP port the virtual server is listening on</i>	Yes
VIRTUALSERVER_AUTOSTART <i>Indicates whether the server starts automatically with the server instance or not</i>	Yes
CONNECTION_FILETRANSFER_BANDWIDTH_SENT <i>Current bandwidth used for outgoing file transfers (Bytes/s)</i>	No
CONNECTION_FILETRANSFER_BANDWIDTH_RECEIVED <i>Current bandwidth used for incoming file transfers (Bytes/s)</i>	No
CONNECTION_PACKETS_SENT_TOTAL <i>Total amount of packets sent</i>	No
CONNECTION_PACKETS_RECEIVED_TOTAL <i>Total amount of packets received</i>	No
CONNECTION_BYTES_SENT_TOTAL <i>Total amount of bytes sent</i>	No

NAME	CHANGABLE
CONNECTION_BYTES_RECEIVED_TOTAL <i>Total amount of bytes received</i>	No
CONNECTION_BANDWIDTH_SENT_LAST_SECOND_TOTAL <i>Average bandwidth used for outgoing data in the last second (Bytes/s)</i>	No
CONNECTION_BANDWIDTH_RECEIVED_LAST_SECOND_TOTAL <i>Average bandwidth used for incoming data in the last second (Bytes/s)</i>	No
CONNECTION_BANDWIDTH_SENT_LAST_MINUTE_TOTAL <i>Average bandwidth used for outgoing data in the last minute (Bytes/s)</i>	No
CONNECTION_BANDWIDTH_RECEIVED_LAST_MINUTE_TOTAL <i>Average bandwidth used for incoming data in the last minute (Bytes/s)</i>	No

CHANNEL PROPERTIES

This is a list of properties available for channels:

NAME	CHANGABLE
CHANNEL_NAME <i>Name of the channel</i>	Yes
CHANNEL_TOPIC <i>Topic of the channel</i>	Yes
CHANNEL_DESCRIPTION <i>Description of the channel</i>	Yes
CHANNEL_PASSWORD <i>Password of the channel</i>	Yes
CHANNEL_FLAG_PASSWORD <i>Indicates whether the channel has a password set or not</i>	Yes
CHANNEL_CODEC <i>Codec used by the channel (see Definitions)</i>	Yes
CHANNEL_CODEC_QUALITY <i>Codec quality used by the channel</i>	Yes
CHANNEL_MAXCLIENTS <i>Individual max number of clients for the channel</i>	Yes
CHANNEL_MAXFAMILYCLIENTS <i>Individual max number of clients for the channel family</i>	Yes
CHANNEL_ORDER <i>ID of the channel below which the channel is positioned</i>	Yes
CHANNEL_FLAG_PERMANENT <i>Indicates whether the channel is permanent or not</i>	Yes
CHANNEL_FLAG_SEMI_PERMANENT <i>Indicates whether the channel is semi-permanent or not</i>	Yes
CHANNEL_FLAG_TEMPORARY <i>Indicates whether the channel is temporary or not</i>	Yes
CHANNEL_FLAG_DEFAULT <i>Indicates whether the channel is the virtual servers default channel or not</i>	Yes
CHANNEL_FLAG_MAXCLIENTS_UNLIMITED <i>Indicates whether the channel has a max clients limit or not</i>	Yes
CHANNEL_FLAG_MAXFAMILYCLIENTS_UNLIMITED <i>Indicates whether the channel has a max family clients limit or not</i>	Yes
CHANNEL_FLAG_MAXFAMILYCLIENTS_INHERITED <i>Indicates whether the channel inherits the max family clients from his parent channel or not</i>	Yes
CHANNEL_NEEDED_TALK_POWER <i>Needed talk power for this channel</i>	Yes
CHANNEL_NAME_PHONETIC <i>Phonetic name of the channel</i>	Yes
CHANNEL_FILEPATH <i>Path of the channels file repository</i>	No
CHANNEL_FORCED_SILENCE <i>Indicates whether the channel is silenced or not</i>	No

CLIENT PROPERTIES

This is a list of properties available for clients:

NAME	CHANGABLE
CLIENT_UNIQUE_IDENTIFIER <i>Unique ID of the client</i>	No
CLIENT_NICKNAME <i>Nickname of the client</i>	Yes
CLIENT_VERSION <i>Client version information including build number</i>	No
CLIENT_PLATFORM <i>Operating system the client is running on</i>	No
CLIENT_INPUT_MUTED <i>Indicates whether the client has their microphone muted or not</i>	No
CLIENT_OUTPUT_MUTED <i>Indicates whether the client has their speakers muted or not</i>	No
CLIENT_INPUT_HARDWARE <i>Indicates whether the client has enabled their capture device or not</i>	No
CLIENT_OUTPUT_HARDWARE <i>Indicates whether the client has enabled their playback device or not</i>	No
CLIENT_DEFAULT_CHANNEL <i>Default channel of the client</i>	No
CLIENT_LOGIN_NAME <i>Username of a ServerQuery client</i>	No
CLIENT_DATABASE_ID <i>Database ID of the client</i>	No
CLIENT_CHANNEL_GROUP_ID <i>Current channel group ID of the client</i>	No
CLIENT_SERVER_GROUPS <i>Current server group IDs of the client separated by a comma</i>	No
CLIENT_CREATED <i>Creation date and time of the clients first connection to the server as UTC timestamp</i>	No
CLIENT_LASTCONNECTED <i>Creation date and time of the clients last connection to the server as UTC timestamp</i>	No
CLIENT_TOTALCONNECTIONS <i>Total number of connections from this client since the server was started</i>	No
CLIENT_AWAY <i>Indicates whether the client is away or not</i>	No
CLIENT_AWAY_MESSAGE <i>Away message of the client</i>	No
CLIENT_TYPE <i>Indicates whether the client is a ServerQuery client or not</i>	No
CLIENT_FLAG_AVATAR <i>Indicates whether the client has set an avatar or not</i>	No
CLIENT_TALK_POWER <i>The clients current talk power</i>	No
CLIENT_TALK_REQUEST <i>Indicates whether the client is requesting talk power or not</i>	No
CLIENT_TALK_REQUEST_MSG <i>The clients current talk power request message</i>	No
CLIENT_IS_TALKER <i>Indicates whether the client is able to talk or not</i>	Yes
CLIENT_MONTH_BYTES_DOWNLOADED <i>Number of bytes downloaded by the client on the current month</i>	No
CLIENT_MONTH_BYTES_UPLOADED <i>Number of bytes uploaded by the client on the current month</i>	No
CLIENT_TOTAL_BYTES_DOWNLOADED <i>Number of bytes downloaded by the client since the server was started</i>	No
CLIENT_TOTAL_BYTES_UPLOADED <i>Number of bytes uploaded by the client since the server was started</i>	No

NAME	CHANGABLE
CLIENT_IS_PRIORITY_SPEAKER <i>Indicates whether the client is a priority speaker or not</i>	No
CLIENT_UNREAD_MESSAGES <i>Number of unread offline messages in this clients inbox</i>	No
CLIENT_NICKNAME_PHONETIC <i>Phonetic name of the client</i>	No
CLIENT_DESCRIPTION <i>Brief description of the client</i>	Yes
CLIENT_NEEDED_SERVERQUERY_VIEW_POWER <i>The clients current ServerQuery view power</i>	No
CONNECTION_FILETRANSFER_BANDWIDTH_SENT <i>Current bandwidth used for outgoing file transfers (Bytes/s)</i>	No
CONNECTION_FILETRANSFER_BANDWIDTH_RECEIVED <i>Current bandwidth used for incoming file transfers (Bytes/s)</i>	No
CONNECTION_PACKETS_SENT_TOTAL <i>Total amount of packets sent</i>	No
CONNECTION_PACKETS_RECEIVED_TOTAL <i>Total amount of packets received</i>	No
CONNECTION_BYTES_SENT_TOTAL <i>Total amount of bytes sent</i>	No
CONNECTION_BYTES_RECEIVED_TOTAL <i>Total amount of bytes received</i>	No
CONNECTION_BANDWIDTH_SENT_LAST_SECOND_TOTAL <i>Average bandwidth used for outgoing data in the last second (Bytes/s)</i>	No
CONNECTION_BANDWIDTH_RECEIVED_LAST_SECOND_TOTAL <i>Average bandwidth used for incoming data in the last second (Bytes/s)</i>	No
CONNECTION_BANDWIDTH_SENT_LAST_MINUTE_TOTAL <i>Average bandwidth used for outgoing data in the last minute (Bytes/s)</i>	No
CONNECTION_BANDWIDTH_RECEIVED_LAST_MINUTE_TOTAL <i>Average bandwidth used for incoming data in the last minute (Bytes/s)</i>	No

DEFINITIONS

The following enumerations can be used to change the behavior of various *ServerQuery* commands:

```
enum HostMessageMode {
    HostMessageMode_LOG = 1,           // 1: display message in chatlog
    HostMessageMode_MODAL,            // 2: display message in modal dialog
    HostMessageMode_MODALQUIT         // 3: display message in modal dialog and close connection
};

enum Codec {
    CODEC_SPEEX_NARROWBAND = 0,        // 0: speex narrowband (mono, 16bit, 8kHz)
    CODEC_SPEEX_WIDEBAND,              // 1: speex wideband (mono, 16bit, 16kHz)
    CODEC_SPEEX_ULTRAWIDEBAND,        // 2: speex ultra-wideband (mono, 16bit, 32kHz)
    CODEC_CELT_MONO                    // 3: celt mono (mono, 16bit, 48kHz)
};

enum TextMessageTargetMode {
    TextMessageTarget_CLIENT = 1,      // 1: target is a client
    TextMessageTarget_CHANNEL,         // 2: target is a channel
    TextMessageTarget_SERVER           // 3: target is a virtual server
};

enum LogLevel {
    LogLevel_ERROR = 1,               // 1: everything that is really bad
    LogLevel_WARNING,                 // 2: everything that might be bad
    LogLevel_DEBUG,                   // 3: output that might help find a problem
    LogLevel_INFO                      // 4: informational output
};

enum ReasonIdentifier {
    REASON_KICK_CHANNEL = 4,          // 4: kick client from channel
    REASON_KICK_SERVER                // 5: kick client from server
};
```